



Alpine Snowdrift Lotion Recipe

Recipe makes approximately 5- 8 oz bottles of lotion.

Here's What You Need:
Ingredients

[Alpine Snowdrift Fragrance Oil](#)

[Stearic Acid](#)

[Silky Emulsifying Wax](#)

[Mango Butter](#)

[Shea Butter](#)

[Sunflower Oil](#)

[Safflower Oil](#)

[Coconut Oil 76](#)

[Vitamin E Oil Tocopherol T-50](#)

[Optiphen Preservative](#)

[Da Bomb Liquid Soap Dye- Blue](#)

[Vanilla White Color Stabilizer](#)

[8 oz Clear Boston Round Bottles](#)

[24/410 White Disc Lids](#)

[Thermometer](#)

Other Ingredients & Equipment You'll Need:

Mixing Bowls

Mixing Spoon

Distilled Water

Stick Blender

Pots (3)

Scale



Here's How It's Done : Directions

Total Recipe Amounts:

784 grams Distilled Water
56 grams Shea Butter
56 grams Mango Butter
28 grams Sunflower Oil
28 grams Apricot Kernel Oil
28 grams Safflower Oil
28 grams Coconut Oil 76
78 grams Silky Emulsifying Wax
34 grams Stearic Acid
6 drops Blue Da Bomb Soap Dye
22 grams Alpine Snowdrift Fragrance Oil
22 grams Vanilla White Color Stabilizer

Clean and sanitize your workstation and all of your packaging materials and utensils. It is suggested that you wear gloves, an apron, gloves, a face mask, and a hair net while preparing this recipe.

Step 1: First, in one of your pots, heat your water. You will want to heat it to at least 180F and hold for 20 minutes to destroy any bacteria. Remove from heat and set aside. Keep in mind, you will have some evaporation. So, you will want to heat extra water so that you will have 784 grams when you are finished.

Step 2: Using a double boiler, melt the stearic acid, emulsifying wax, shea butter, mango butter, sunflower oil, apricot oil, safflower oil, and coconut oil.

Step 3: When both the water and pot containing the melted oils, butters, and waxes are at 140 degrees Fahrenheit combine them. Use a stick blender to emulsify them.

Step 4: Finally, when the ingredients are at about 120 degrees Fahrenheit, add the fragrance oil, vitamin E oil, and Optiphen. Once again, use your stick blender to incorporate the ingredients together.

Step 5: Allow the cream to come to room temperature, stick blending periodically as it is cooling. As it cools it will continue to thicken.

Step 6: Place the body cream in the jars. Put a lid on each jar.

Your Alpine Snowdrift Lotion is now ready to use!

Natures Garden is not responsible for the performance of any of the recipes provided on our website. Testing is your responsibility. If you plan to resell any recipes we provide, it is your responsibility to adhere to all FDA regulations if applicable. If there are ingredients listed in a recipe that Natures Garden does not sell, we cannot offer any advice on where to purchase those ingredients. We also do not offer any advice on formulating or altering recipes.