



Green Clay and Charcoal Soap Recipe

Recipe makes approximately 2.25 pounds of soap.

Here's What You Need:
Ingredients

[Lye- Sodium Hydroxide](#)

[Coconut Oil 76](#)

[Apricot Kernel Oil](#)

[Castor Oil](#)

[Sunflower Oil](#)

[Mango Butter](#)

[Shea Butter](#)

[Palm Oil](#)

[Lemon Verbena Fragrance Oil](#)

[French Green Clay Powder](#)

[Activated Charcoal Powder](#)

[Mitre Box](#)

[Cutter for Mitre Box](#)

[Neon Green FUN Soap Colorant](#)

[Safety Glasses](#)

[Safety Gloves](#)

Other Ingredients & Equipment You'll Need:

Mixing Bowls

Mixing Spoon

Scale

Stick Blender

Vinegar

Distilled Water

Loaf Mold



Here's How It's Done : Directions

Total Recipe Amounts for Green Soap:

180 grams Distilled Water
66 grams Lye

79 grams Sunflower Oil
18 grams Castor Oil
33 grams Apricot Kernel Oil
141 grams Coconut Oil 76
66 grams Mango Butter
61 grams Shea Butter
71 grams Palm Oil

3 drops Neon Green FUN Soap Colorant
10 grams French Green Clay Powder
(mixed with a small amount of soaping oils)

Total Recipe Amounts for Black Soap:

180 grams Distilled Water
66 grams Lye

79 grams Sunflower Oil
18 grams Castor Oil
33 grams Apricot Kernel Oil
141 grams Coconut Oil 76
66 grams Mango Butter
61 grams Shea Butter
71 grams Palm Oil

2 grams Activated Charcoal Powder
(mixed with a small amount of soaping oils)

Step 1: First, prepare both of the lye solutions. Set them aside for now.

Step 2: Next, prepare the soaping oils for each batch.

Step 3: Prepare your first batch. Add the first lye solution to one of the bowls of soaping oils. Stick blend to emulsify.

Step 4: Now, add the fragrance oil and the activated charcoal mixture. Once again, stick blend.

Step 5: Place your loaf mold in front of you. Prop it up at a 45-degree angle. Then, pour the soap into the mold. Allow it to set up for about 10-15 minutes.

Step 6: At this time, prepare the next batch of soap. Once your lye solution and soaping oils are emulsified, add the fragrance oil and green clay mixture. Once again, stick blend.



Here's How It's Done : Directions

Step 7: Set the mold flat in front of you. When your soap batter reaches trace, pour the second batch of soap batter into the soap mold. Tap the mold on the countertop to release any air bubbles.

Step 8: Once your soap has set up for 24-48 hours, cut it. Once cured, it will be ready to use!

Natures Garden is not responsible for the performance of any of the recipes provided on our website. Testing is your responsibility. If you plan to resell any recipes we provide, it is your responsibility to adhere to all FDA regulations. If there are ingredients listed in a recipe that Natures Garden does not sell, we cannot offer any advice on where to purchase those ingredients.